CONFCNTLR: A VIDEOCONFERENCE CONTROLLER

A thesis submitted to the faculty of San Francisco State University in partial fulfillment of the requirement for the degree

Master of Science in Computer Science

by

Marcia Ann Perry

San Francisco, California

December, 1997

Copyright by Marcia Ann Perry 1997

CERTIFICATION OF APPROVAL

I certify that I have read *Confcntlr: A Videoconference Controller* by Marcia Ann Perry, and that in my opinion this work meets the criteria for approving a thesis submitted in partial fulfillment of the requirements for the degree:

Master of Science in Computer Science at San Francisco State University.

William Tsun-Yuk Hsu Associate Professor of Computer Science

-_____

C. S. James Wong Associate Professor of Computer Science

Deborah A. Agarwal Staff Scientist, Lawrence Berkeley National Laboratory CONFCNTLR: A VIDEOCONFERENCE CONTROLLER

Marcia Ann Perry
San Francisco State University
1997

Multicast over the Internet has inspired research into building virtual laboratories and developing multimedia conference tools. The Spectro-Microscopy

Collaboratory, under development at Lawrence Berkeley National Laboratory and the University of Wisconsin, Milwaukee, is a project aimed at making virtual laboratories a reality. *Confcntlr* was developed for use in this collaboratory as a conference controller to enhance the usability of the videoconference tools. It allows local and remote control of the audio and video and provides an integrated interface to the media tools. *Confcntlr* has changed the paradigm of videoconferencing so that users do not have to be present at the transmitting site. By presenting a unified interface, it facilitates the management of multiple tools running concurrently. This thesis describes the design, development, and implementation of *confcntlr*, and discusses recent work in videoconference tools, control, and coordination.

I certify that the Abstract is a correct represer	ntation of the content of this thesis.
William Tsun-Yuk Hsu Associate Professor of Computer Science	Date

ACKNOWLEDGMENTS

I would like to thank my advisor Dr. Deb Agarwal for her guidance and for having provided me with the opportunity to design and develop this thesis. I would also like to thank my thesis committee members, Dr. Bill Hsu and Dr. James Wong, for their support and instruction. Much appreciation also goes to my fellow students and co-workers at LBNL who are always willing to share information, especially John Taylor who patiently answered my Frame questions.

This work is supported by the Director, Office of Energy Research, Office of Computation and Technology Research, Mathematical, Information, and Computational Sciences Division, of the United States Department of Energy under Contract No. DE-AC03-76SF00098 with the University of California.

TABLE OF CONTENTS

List of Figures	'iii
List of Appendices	X
1 Introduction	2 4
2 Background	6 7 13
3 Software Architecture.23.1 Requirements23.1.1 Design Requirements23.1.2 Functional Requirements23.2 System Overview2	21 21 23
4 Implementation	29 31 32
5 Algorithms	39 40 41 43 45

6 Summary and Future Work	55
References	58
Appendices	61

LIST OF FIGURES

1 The primary <i>vic</i> user interface panel with an expanded view of the incoming video feed shown below it11
2 Vic's menu window reached by pressing "menu" on the vic panel11
3 The <i>vat</i> user interface
4 The wb user interface
5 Sdr's main window shows the currently advertised sessions
6 <i>Sdr</i> 's session information window
7 <i>Sdr</i> 's session creation window17
8 The Conference Bus
9 Confcntlr's Components25
10 Communication Channels
11 <i>Confcntlr</i> 's main window
12 The Conference window
13 Main window with pulldown menus
14 Menu for setting remote <i>vic</i> and <i>vat</i> controls
15 Advanced Audio WIndow
16 The Security Window
17 Prompt Panel to Approve a Remote Request for Setting Changes 38
18 Warning Panel for Notification of Changes Made by a Remote Host 38
19 Warning Panel to Display Denial of Setting Changes

20 Warning Panel to Display Denial of Action
21 Initialization
22 Termination
23 Starting <i>vic</i> and <i>vat</i> on Local Host
24 Stopping vic and vat on Local Host
25 Changing Local <i>vic</i> or <i>vat</i> Settings43
26 Sending a TCP Message
27 Receiving a TCP Message
28 Requesting a Remote Operation
29 Processing a TCP Request
30 Changing Parameter Values
31 Starting <i>vic</i> or <i>vat</i> in Response to Remote Request50
32 Changing <i>vic</i> or <i>vat</i> Settings in Response to Remote Request 51
33 Sending Local Settings 52

LIST OF APPENDICES

Α	Further Inf	ormati	on		 	 	 	 	٠.	٠.	 	 		 		 . 6′
В	Confentlr.	User I	Manua	al.	 	 	 	 				 	 	 		 . 62

Chapter 1

Introduction

Recent advances in network and computer technology have made it possible for users at remote locations to actively participate in scientific research without traveling to laboratories where the experiments are being conducted. It is possible to receive data and observe analysis results, and to control the instruments and collaborate with other remote scientists within a distributed electronic environment. In 1993, the National Research Council stated that

"The fusion of computers and electronic communications has the potential to dramatically enhance the output and productivity of US researchers. A major step toward realizing that potential can come from combining the interests of the scientific community at large with those of the computer science and engineering community to create integrated, tool-oriented computing and communications systems to support scientific collaboration. Such systems can be called 'collaboratories' "[4].

Building virtual laboratories has become an active field in which emerging technology, work in distributed computing, and data management have been recently applied to provide location-independent access to data, equipment, and collaborators.

1.1 The Spectro-Microscopy Collaboratory

The United States Department of Energy has funded a series of four projects to develop, implement, and integrate the technology required to make virtual laboratories a reality. These projects are called the "Distributed Collaboratory Experiment Environments Program" (DCEE)[2].

One DCEE project is the Spectro-Microscopy Collaboratory, which is under development at Lawrence Berkeley National Laboratory (LBNL) and the University of Wisconsin, Milwaukee. This collaboratory provides researchers from large and geographically distributed centers remote access to a synchrotron-radiation beamline and to the analytical tools at LBNL's Advanced Light Source (ALS). The various components of the collaboratory allow remote equipment control, environment monitoring, data collection, a shared view of the data and results, and communication between participants[1].

Videoconference tools are used to facilitate person-to-person interaction.

The videoconference tools utilized by the Spectro-Microscopy project researchers are: *vic* for transmitting and receiving video images, *vat* for transmitting and receiving audio signals, *wb* (whiteboard) for shared drawing and sending and receiving slides, and *sdr* (session directory) for identifying and launching conferences that are being broadcast. These tools have been built upon the IP multicast

capability, which provides efficient multi-point communication. Multicasting has been implemented by building a virtual network on top of the Internet, which is called the Multicast Backbone, or MBone[16]. (See Appendix A for pointers to MBone tools and information.)

The *vic* and *vat* tools allow researchers at the ALS to start the video and audio on the local computer and transmit the images and sound to either a unicast or multicast address. Users at a remote site can receive the video and audio by starting *vic* and *vat* on their local hosts. The *sdr* tool lists the conferences that are broadcasting and allows users to select the conference and start *vic* and *vat* locally from *sdr* windows.

While these tools represent a large technological advancement, they can be enhanced further. Each one of them has a separate interface and none can be controlled remotely. Users cannot use *sdr* to change the local *vic* or *vat* parameters; they must manipulate controls on the *vic* or *vat* windows. Also, none of these tools allows a user at one host to launch or stop the videoconference tools on another host or to change the parameters on a remote site once a tool has been started. For example, if the computer at the ALS is not running *vic* or *vat*, users at the University of Wisconsin, Milwaukee cannot start a video or audio tool on the ALS computer with *vic*, *vat*, or *sdr*. If the computer at the ALS is transmitting video at a certain bandwidth and a frame rate, users in Milwaukee cannot change these

values nor can they turn remote video transmission on or off.

Inability to adjust video or audio parameters remotely can be frustrating to the remote participant. Furthermore, because the video feed can take up a large amount of bandwidth and potentially saturate the network, there are times when the transmission rate and bandwidth should be reduced (e.g., when there are no remote users watching the video). This currently requires a human operator at the computer that is transmitting the video, which can be a burden to the researchers who are conducting the experiments. The computer technology and tools that allow remote participation in an experiment should not take a researcher away from the experiment itself; nor should they require that researchers spend a great deal of time managing the conference session.

1.2 The Conference Controller

ConfentIr was developed for use in the Spectro-Microscopy Collaboratory project as a conference controller. It is a new MBone tool that works in conjunction with other videoconference tools to enhance the usability of video and audio. It allows local and remote control of the audio and video tools and provides a single interface to vic and vat. Users at one site can start a video or audio session at another site and can specify the parameter values. Once vic or vat is running, remote users can change the video or audio settings without stopping and restarting the

tools and they can turn video transmission on or off without stopping and restarting *vic*.

By providing remote control of video and audio tools, *confcntlr* has changed the current paradigm of videoconferencing so that users do not have to be present at each feed. By presenting a unified interface for these tools, it facilitates the management of multiple tools running concurrently. (See Appendix B for the *confcntlr* user manual.)

1.3 Thesis Organization

This document describes the design, development, and implementation of *confentlr*, a conference controller which aims to further the collaboratory effort by enhancing the usability of existing videoconference tools. The next chapter will survey the multicast network infrastructure and discuss recent work in videoconferencing. Chapter 3 will present the conference controller's architecture. Chapter 4 will discuss the design and implementation of *confentlr*. The algorithms used by *confentlr* will be described in chapter 5. Chapter 6 will summarize the thesis, identify further needs, and suggest additional features for *confentlr*.

Chapter 2

Background

Recent research in the development of multicast-based multimedia conferencing tools for the public domain has led to the development of media tools, conference management tools, and conference control protocols. Since most of the tools were built upon the MBone, the chapter begins with a description of IP multicast and the MBone.

2.1 Multicast Backbone (MBone)

Unicasting provides point-to-point communication in which one host is specified as the destination for network packets. Broadcasting allows transmission to multiple destinations simultaneously and therefore has the potential to scale well to large numbers of receivers. With broadcasting, all hosts on a network receive copies of the packet being transmitted. With multicasting, IP datagrams are sent to all hosts listening on a multicast group address. Each group has a unique IP multicast (class D) address; a multicast group consists of hosts that want to get packets with the specified class D address. These groups are dynamic; hosts may join or leave a multicast group at any time[6].

The multicast backbone, or MBone, implements IP multicast. It is a new technology which has not yet been fully deployed to all routers and hosts on the Internet. When a host wants to join a multicast group, it issues a request to do so and then receives packets transmitted to the specified multicast address. A host can transmit packets to a multicast address without knowing which sites will receive them; the receivers have the responsibility of joining the group. To limit the scope of a multicast packet, a time-to-live (TTL) value is specified. The TTL is decremented each time that it is received by a router. When the TTL is less than the link threshold, the packet is not forwarded. By convention, a TTL between 1 and 16 would be used to keep packets within a single network while a TTL of 127 would be specified for global traffic.

2.2 Media Tools

Videoconferencing tools for sending and receiving media streams may be independent, standalone applications, or they may be components that work together within a multimedia conferencing system. Media include video, audio, and shared workspaces on which conference participants may write or draw. This section will discuss *Net Video* from Xerox PARC, *IVS* and *Rendez-Vous* from INRIA, and *vic*, *vat*, and *wb* from Lawrence Berkeley National Laboratory. All of these tools are based on a replicated architecture and all use the Real Time Protocol (RTP) on top of IP Multicast. RTP contains a data delivery protocol to handle the actual

media transmission and a control protocol to manage information such as sender identification and to provide time-stamping, packet sequencing, and receiver feedback.

Net Video, or *nv*, provides video-only conferencing and is one of the earliest MBone tools. It allows users to send and receive slow frame rate video as point-to-point or multicast streams[25]. *nv* uses a software-based codec and a custom coding scheme that has low computational complexity. Its graphical user interface allows users to select a video stream from among those displayed, set parameters, and view conference information. Video parameters include grabber controls and transmit and receive options (e.g., size and color).

The INRIA Videoconferencing System (*IVS*) was developed at the same time as *nv*. It transmits real-time audio and video over the MBone[25]. The audio codecs are PCM and ADPCM. The video codec is a software implementation of the H.261 standard which provides a video compression algorithm that can achieve a very high compression rate. Thus, while its simpler encoding gives *nv* better run-time performance, *IVS* uses less bandwidth. However, the H.261 standard was originally developed for the Integrated Services Digital Network (ISDN), which can provide better quality of service (QoS) than the Internet because of its guaranteed bandwidth. To maintain good QoS while minimizing bandwidth, *IVS* implemented schemes to adapt the H.261 video compression algorithm to the

Internet environment. These schemes included packetization, error control, and output rate control. The packetization scheme formats RTP and H.261 header information and uses macroblock fragmentation of the payload. Since UDP packets may be lost or arrive out of sequence, an error control scheme was implemented to mitigate against packet loss. In order to control network congestion, *IVS* adapts its video output rate to network conditions. *IVS* allows users to call up and talk to someone on the Internet. It also displays a list of participants and the media they are using[24].

Rendez-Vous is under construction as the successor to IVS[15]. It provides video and audio within one application. It is described as an integrated scheduler for media flow management and processing, which optimizes resources to maximize the quality rendered to the user. The audio component is an integration of the FreePhone audio tool, recently developed at INRIA. The basic features of Rendez-Vous include: support of RTP over multicast or unicast IP, the H.261 video standard, high-quality PCMU, ADPCM, UADPCM with HiFi support and low-bandwidth GSM and LPC audio encoding. Advanced features include: flexibility for inserting new protocols and coding schemes, multi-level audio redundancy for bad network links, dynamic media rate control (i.e., adaptation to match the available bandwidth), support for layered coding and transmission of media flows, and multiresolution wavelet and discrete cosine transform (DCT) codecs.

Vic, vat, and wb are separate but interoperable applications. Vic is a visual tool; vat is an audio tool; and wb is a shared whiteboard. Vic and vat extend the work of nv and IVS with a more flexible system architecture that supports hardware-based codecs and a variety of compression algorithms, a model for conference coordination, and an extensible user interface. These tools implement a software decoder for each supported compression format so that, if a sender uses a hardware codec, all receivers can decode the stream. Vic and vat support a variety of formats. Vic's encoding scheme gives better compression performance compared to nv and better runtime performance and packet-loss tolerance compared to IVS. Vat has mechanisms to dynamically adapt itself to network delays, supports several methods of avoiding feedback or echo from the microphone to the speaker, and supports different modes of interaction (e.g., lecture mode in which the speaker's microphone is continuously open and "push-to-talk" in which users push a button to open their microphone and release it when they are finished)[17]. More recently, vat has supported the use of a hardware echo canceller for hands-free operation.

Interprocess communication for application interoperability is achieved by local multicasting through a communication channel termed the "Conference Bus." Each application that is connected to this channel can broadcast messages and all processes that are connected to the channel get a copy of the message. Each conference has its own conference bus to coordinate the media within that ses-

sion. For example, *vic* can focus on the current speaker using cues from *vat* and floor control can be supported (e.g., a directive can be broadcast to let receivers ignore the media from all participants except the one who holds the floor). There is also a global conference bus for interaction among different sessions, such as for access to shared video and audio devices.

The controls for *vic* and *vat* allow users to set a wide variety of parameters and change them while the programs are running. Both tools keep track of and display a list of participants and allow users to mute and unmute media sources. Users can augment or change the behavior of these tools by writing their own scripts which are evaluated by *vic* or *vat*. Figures 1 and 2 show *vic*'s user interface and Figure 3 shows *vat*'s user interface.



Figure 1: The primary *vic* user interface panel with an expanded view of the incoming video feed shown below it.




Figure 2: *Vic*'s menu window reached by pressing "menu" on the *vic* panel. The list of members is shown to the right of the *vic* menu.




Figure 3: The vat user interface. The window on the right depicts the menu window.

wb provides a shared whiteboard on which users may draw or write. When a change is made, updates are made to all participants' workspaces simultaneously. Since it can import PostScript files, wb can be used to send slides. Figure 4 shows wb's user interface.




Figure 4: The *wb* user interface. The user information window is shown on the left.

2.3 Conference Management Tools

Conference control has included: session creation, announcement, and control; application control; floor control; and resource management. Session creation encompasses allocating addresses and specifying the information necessary to start the conference with the correct initial state (e.g., session identifer and media tools). Session announcement includes directory services to advertise availability and methods of rendezvous. Session control entails managing participation (e.g., who is sending and receiving what media), authentication (e.g., session identification, encryption keys), and presentation of coordinated user interfaces. Application control refers to the ability to start and stop media applications and change

media-specific features locally or remotely. Floor control is the management of media access (e.g., who can send audio or video and which streams can be muted by receivers). Resource management includes conference scheduling (i.e., booking systems) and the allocation and management of bandwidth to avoid network congestion. At lower levels, conference control has included connection control and protocol conversion to support different networks (e.g., ISDN and packet networks)[9,13,20].

While some of the media tools discussed above provide some control functions, external management tools have been developed as separate applications or components of conferencing systems. The control tools presented below are: the Multimedia Conference Control program (*MMCC*) from USC/ISI, the Session Directory Tool (*sdr*) from MICE/ESPRIT, the Integrated Session Controller (*ISC*) from FOKUS, and *TelePort* from LUTCHI.

MMCC was developed as a prototype session orchestration tool for point-to-point and multipoint multmedia conferences[21]. Its main functions are to supply session creation and maintenance services and to manage the media. The media tools are separate applications and include *vat*, *nv*, and *wb*. Built on a distributed, peer-to-peer model, *MMCC* is meant to execute continuously on a work-station residing at each conference site. The media tools may be executed on a separate machine. Conference participation is by invitation only.

To establish a conference, a user enters the required information and invites other users to participate. *MMCC* allows a caller to explicitly invite others to join a conference and alerts them to accept or decline. When a user creates a session, MMCC assigns a conference address and identifier, spawns the selected media tools with the specified configuration (e.g., device, bandwidth, and coding algorithm) if it can be met, and alerts the callee to accept or decline the invitation. An "autopilot" facility allows callees to automatically accept or decline invitations. When a participant leaves the conference, MMCC tears down the media. MMCC allows remote control of data rate and hardware devices (e.g., cameras, codecs, and monitors). Although the actual data flow is left to the individual media components, MMCC passes session and control information to them and to other MMCCs. This information includes lists of participants and timing information for inter-media synchronization. *MMCC*s use the Connection Control Protocol (CCP) to communicate with each other. Multicasting of control information is via sequential unicast rather than via the MBone.

The *sdr* session directory is an MBone conference scheduling and booking system. It has been described as an "Electronic TV Listings Guide" [5]. Events are either broadcasts or interactive meetings, using a variety of media tools. *Sdr* supports public and private sessions and performs the following basic tasks: listening for announcements and listing sessions; starting the relevant media tools; creating sessions; and allowing users to make private "phone calls" to other users.

It utilizes the following protocols: Conference Control Channel Protocol (CCCP), Session Description Protocol (SDP), Session Announcement Protocol (SAP), and Session Initiation Protocol (SIP). Figure 5 shows the main window. When a user clicks on a session title, a "Session Information Window" (shown in Figure 6) appears to allow users to join a session, invite others to do so, or record media.



Figure 5: *Sdr*'s main window shows the currently advertised sessions.



Figure 6: *Sdr*'s session information window. The tools and multicast addressing information is listed along with a description of the session.

As shown in Figure 6, session information is displayed along with the tools used in the conference. A user can start the tools singly or join the conference by starting all of them. Additionally, users can access a web page by clicking on the "More Information" button and they can view the names and locations of the session creators by clicking on the "Contact Details" button. To set up a conference, the creator must specify the information necessary to advertise and start the conference. The standard tools supported are: *vat* and *rat* for audio, *vic* and *nv* for video, *wb* for whiteboard, and *nt* for text. New media and new tools for existing

media may be defined. A session creation window is shown in Figure 7.



Figure 7: *Sdr*'s session creation window. This window is used to create a conference session.

ISC is one component of the Multimedia Internet Terminal (MInT) conferencing system, which is currently under development[22]. ISC is a central conference controller that interoperates with the other components of the system, namely, media agents and auxiliary controllers. The media agents include the Network Video Terminal (NeViT) and vic for video and the Network Voice Terminal (NeVoT) for audio. The media agents provide unicast and multicast sessions over RTP/UDP/IP. Auxiliary controllers include the Session Invitation Terminal (SInT), a reservation agent, and a floor controller. ISC provides an integrated graphical user interface for the media and conference controls. While NeVoT has its own

graphical user interface, NeViT does not; it is controlled through ISC.

ISC allows users to establish conferences and invite other users to participate. It also manages conference parameters and displays the participants and their status (which media they are using and whether they are sending or receiving). To create a conference, users specify the media and their settings (e.g., encoding, maximum bandwidth, maximum frame rate, and quality) and the network configuration (e.g., UDP or ATM and parameters such as burst length and peak bandwidth). If the requested configuration is available, ISC starts the media on the local host. *ISC* also supports bandwidth reservation using the reservation agent as an interface to an RSVP daemon. To invite another user to participate in the conference, the caller enters the email address of the callee. ISC forwards this address to SInT which, through the use of daemons, verifies what host the callee is logged onto and sends the invitation request. The remote ISC receives the request, displays a panel used to accept or reject the invitation, starts the media if the request is accepted, and sends a reply. During the conference, the participants' list can be used to enable or disable receiving media streams. Additionally, NeViT adapts its sending behavior to the congestion state of the network (i.e., it reduces its sending rate when large losses are reported in the received RTCP packets). ISC is used to turn this algorithm on or off and to set its parameters. ISC also displays network traffic statistics such as bandwidth, loss, and jitter values.

Communication between *ISC*s is via TCP connections. Communication between components on the same host is via local multicast, if it is supported. If local multicast is not supported, *MInT* uses a "message replicator," which is a separate process that forwards control messages to controllers and media agents, using the "pattern-matching multicast communication protocol" (PMM). The goal in designing *MInT* was to obtain the benefits of both tightly-coupled and loosely-coupled architectures. Since the media agents are separate applications, they can be replaced, updated, and reused. *ISC*'s integrated user interface makes these tools more manageable and the use of local multicast (or PMM) allows the interoperability of the independent controllers and media agents. However, once a media tool has been started, its settings cannot be changed by a remote site.

TelePort is under construction as a research vehicle for the study of issues in the design of multimedia communication systems interfaces[3]. It interacts with vic, vat, and wb, and can be launched from sdr. TelePort provides users with awareness of what other participants in a group are doing--how busy they are, whether they can be interrupted, who they are talking to, and whether they are available for collaboration. It uses the metaphor of the office door to represent a user's availability. Users set options such as "working hard" and choose icons to indicate whether their doors are open or closed. The main window displays these options as well as the video and audio capability (e.g., "no speaker, no microphone," "no speaker, have microphone," "have speaker, no microphone," or "have

speaker, have microphone"). The availability state of remote users and a list of participants are also displayed. Control packets are multicast according to an experimental "Group Awareness Protocol" (GAP). Group members usually belong to a work or project group and explicitly join a *TelePort* session. *TelePort* emphasizes the use of social, rather than technological, methods of multimedia session control. It builds upon current work in the development of "Media Spaces." It is described as a proof of concept prototype of the effectiveness of the principles underlying the "Social Computer"--a system that allows users to apply their knowledge of social protocols in deciding what they should do rather than embedding social rules within the system.

2.4 Summary

Work in the multimedia conferencing area has been largely concerned with the development of media tools and their infrastructures. Attention has been given to improving the quality of service while minimizing bandwidth. It is only recently that research has been devoted to conference control. Some efforts have emphasized conference system architecture while others have emphasized usability or functionality (e.g., session creation, announcement, and invitation). However, remote control capabilities have been limited to starting tools on remote sites, not to changing remote settings while a tool is executing. Users must operate the tools at both the sending and receiving sites and thus divide their time between conference participation and manipulation of videoconference tools.

Chapter 3

Software Architecture

Confcntlr was built to control videoconference tools locally and remotely through a unified interface. This chapter will define the conference controller's requirements more specifically and explain its basic components. The implementation will be explained in terms of the interoperability of these components in Chapter 4.

3.1 Requirements

The following sections delineate the features that must be included in the design of the conference controller and the actions that it must perform.

3.1.1 Design Requirements

The major design requirements are a graphical user interface and a communication system. The communication system permits data exchange between *confentlr*s running on remote hosts and between *confentlr* and videoconference tools running on the same host. The graphical interface has to be intuitive to users and unobtrusive. It is meant to replace the independent media interfaces or be used in conjunction with them. Because the conference controller allows remote control of other tools, security is also an important feature

Since remote control requires data exchange between conference controllers on different hosts, a reliable message-based mechanism is required for sending and receiving requests and replies. In addition to communicating with other
hosts and processes, users must be able to manipulate controls in the graphical
user interface at all times. Therefore, *confcntlr* has to be nonblocking. Once a
message has been sent, the user should not be prevented from further operation
because *confcntlr* is waiting for a reply. To ensure that all sites could be considered equal, a peer-to-peer rather than client-server paradigm is required.

Vic, vat, and wb use the local multicast "conference bus" for coordination of a videoconference session[17]. A design requirement for the conference controller is to utilize the conference bus for communication with the other videoconference tools. Because the hardware can support multiple video cards, one host must be able to execute more than one video tool. It is also possible to execute multiple audio tools. Therefore, the conference bus is shown in Figure 8 as a communication channel between any number of video and audio tools.




Figure 8: The Conference Bus. *Confcntlr* can exhange information with any number of video and audio tools running on the same host.

3.1.2 Functional Requirements

The major functional requirements were to allow users to view and change parameters, carry out operations for local and remote control of video and audio, provide security features, and display the system status. The parameters include the conference name and address, time-to-live, and values specific to each medium (e.g., video bandwidth, frame rate, quality, device, compression format, and transmission).

The actions that must be supported are the following:

- start a specific video or audio tool on the local or remote host with userselected parameter values
- start all video and audio tools on the local or a remote host with userselected parameter values
- stop a video or audio tool running on the local or remote host
- obtain a remote host's settings and find out which videoconference tools are running on that host
- change parameter values for a video or audio tool that is already executing
- turn video transmission off and on while the video tool is running

Since communication between conference controllers is over the public Internet, confidentiality and integrity of data must be preserved. Thus, the conference controller must support encryption. Messages sent to a remote host can be encrypted and messages received can then be decrypted, using an agreed upon key that users can change. Also, users must be able to turn off encryption if they wish. The conference controller has to detect whether data read from the network has been encrypted or not.

To provide uninterrupted media and protect computer resources, the conference controller should be able to restrict remote access to authorized users and hosts. Local users should be able to restrict actions such as having the video or audio turned on and off. Also, since exceedingly high bandwidths or frame rates could saturate the network, users should be able to monitor or limit changes in these values.

The required security features are:

- encryption/decryption of data exchanged between conference controllers at remote sites
- detection of whether data is or is not encrypted
- allowing users to change the encryption key
- allowing users to turn off encryption
- capability of restricting control of the conference controller to authorized users and hosts
- capability for users to grant or deny permission for another host to change values or perform an operation (unconditionally or on a per change-request basis)
- ability to provide warnings when changes are made

3.2 System Overview

The conference controller was built to work with *vic* and *vat*. The conference controller has four components that work together to provide the necessary functionality. These components are:

- graphical user interface
- control unit
- network unit
- encryption unit

The graphical user interface (GUI) receives user input and displays output. The control unit contains the functions to set values or carry out actions. Although not directly visible to the user, this is perhaps the locus of the main work of the conference controller. Transparent to the user and at a lower layer is the network unit that provides the mechanism for host-to-host and interprocess communication. It is invoked whenever messages need to be exchanged and, in turn, invokes the encryption unit when these messages are transmitted or received over the network. Figure 9 shows the relationships of the four components.




Figure 9: *Confcntlr's* Components. The arrows indicate the data flow.

All actions go through the control unit. When a user manipulates a control in the graphical user interface, values are set or actions are carried out by functions in the control unit. If a message is to be sent to a remote host or to a video-conference tool on the same host, the control unit invokes the network unit. The network unit invokes the encryption unit only when messages are sent to or received from a remote host. When a message is received by the network unit (from either a remote host or from the video or audio tools on the same host), the control unit processes the message and the graphical user interface displays the output.

The network component is responsible for establishing connections and transmitting and receiving data over the communication channels to support host-to-host and interprocess message exchange. Figure 10 depicts these communication channels.




Figure 10: Communication Channels. A TCP connection is for peer-topeer communication while the conference bus is used for interprocess communication within a single host.

Data transfer between conference controllers running on different hosts is via the Transmission Control Protocol (TCP), which provides reliable, ordered, unicast delivery[6]. The communication required to satisfy a request may be half-duplex or full-duplex, depending upon whether a reply or acknowledgment is required. Data transfer between applications running on the same host is via the multicast conference bus local to the host.

Chapter 4

Implementation

Confcntlr was implemented on SUN workstations running the Solaris 2.5.1 operating system and ported to Silicon Graphics workstations running the Irix 6.2 operating system. It was written to control *vic* and *vat*. Although one *confcntlr* controls one conference session, multiple *confcntlr*s can be run to allow users to participate in multiple conferences. To obtain directory and booking services, *confcntlr* can be launched from *sdr*. *Confcntlr* is a single-threaded application that does all of its processing within an event loop. Host-to-host and interprocess communication were implemented with the socket interface[23].

The Data Encryption Standard (DES) was used for encryption[8]. The network and encryption units and part of the control unit were written in the C programming language. The graphical user interface and most of the control unit were written in Tcl/Tk[18,26]. Tk is well-suited for creating windows for the X Window System, which is employed by Solaris. Tcl provides an interface to C that makes it possible to write applications in a combination of C and Tcl/Tk. It also provides an event loop and a simple way to do nonblocking, nonsequential I/O.

The implementation of each functional component will be discussed in the following sections. The algorithms, presented in Chapter 5, will describe the way

confentlr works and how these components operate together.

4.1 The Control Unit

The control unit carries out local operations invoked by the GUI or network unit. These operations include starting and stopping *vic* and *vat* or changing the settings for a tool that is executing on the local host. The control unit also formats requests for and replies to operations on remote hosts.

When the GUI invokes the control unit to start (or stop) a tool on the local host, the control unit spawns (or terminates) a process for the tool selected.

When a user changes a local *vic* or *vat* setting and the tool is running, the control unit formats a message and invokes the network unit to transmit the message via the conference bus. When a user initiates a remote operation, the control unit formats a message and invokes the network component to establish a connection and send the request.

If a message arrives from *vic* or *vat* on the conference bus, the control unit updates its settings and invokes the GUI to display the new values or status. For example, if the user clicks the "quit" button in the *vic* or *vat* window, a message is broadcast on the conference bus. *Confcntlr*'s network unit forwards the message to the control unit, which determines which tool sent the message, updates the

required values, and then invokes the GUI to display the new status. If a remote host requested starting the tool, that host is sent a termination notice. If the user changes a setting in the *vic* or *vat* window (e.g., video transmission or audio input or output gain), a message is also broadcast to the conference bus and again *confentli*'s network unit forwards the message to the control unit which updates the appropriate parameter and invokes the GUI to update *confentli*'s display.

When the network unit receives a request, reply, or notification from another *confcntlr* running on a remote machine, it forwards the message to the control unit for identification and processing. Upon receiving a request, the control unit identifies the action and invokes security functions (e.g., checking the authorization level and prompt options). It invokes the GUI to display prompt panels when the user wants to manually set permissions. The requested action is carried out only if permission is granted. The control unit formats a reply for every request that it processes and forwards the reply to the network unit for transmission.

Upon receiving a reply or notification, the control unit updates values and calls the GUI to update the display (e.g., remote settings were sent, a request was denied, or a remote tool was terminated by its local user). If a request is denied, the control unit invokes the GUI to create and display a warning panel.

4.2 The Network Unit

The network unit is responsible for opening and closing communication channels and sending and receiving data. The sockets for sending and receiving messages over the conference bus and the socket on which the conference controller listens for TCP connection requests are opened once and remain open for the duration of the program. A separate TCP connection is opened and closed for each remote operation. To allow the conference controller to function as a sender or receiver at all times without blocking, a file handler is created when a socket is opened. The file handler arranges for the appropriate procedure to be invoked whenever data arrives on the socket.

The network component is responsible for host-to-host and interprocess communication. There are two host-to-host communication schemes.

- Host A sends a request to host B. Host A does not wait for a reply unless it is obtaining a remote host's settings. Host B receives the request, processes it, and sends a reply.
- 2. Host A notifies host B that some event took place (e.g., host A terminated a process). Host B receives and processes the notification but does not send a reply.

Interprocess communication works as follows. Messages sent to other applications running on the same host are broadcast via the conference bus. Each application that is connected to this channel receives a copy of the message and, if an application recognizes the message type, it processes the message

locally and may also forward that message to a conference controller at a remote site. Acknowledgments and replies are not sent. Events that are broadcast are the following:

- vic or vat was terminated and wants to notify the conference controller
- the conference controller wants to dynamically change a setting on vic or vat
- vic or vat changed its setting and wants to notify the conference controller

4.3 The Encryption Unit

Because encryption routines are not currently allowed to be exported from the United States and *confcntlr* was to be placed on the World Wide Web, two versions of the conference controller were built, one that supports encryption and one that does not. We'll refer to these in this section as *confcntlr-crypt* and *confcntlr*, respectively.

The encryption component of *confcntlr-crypt* invokes functions from the SSLeay library to encrypt plain text and decrypt ciphertext, using the key provided by the caller (the network unit). The encryption unit of *confcntlr* returns immediately if the encryption and decryption functions are called. With the exception of the encryption component, both versions of the conference controller have the same code. The different versions are built by compiling and linking with the appropriate encryption components.

A conference controller that supports encryption is able to control a conference controller that does not, but the reverse does not hold. The encryption unit tells the network unit whether or not the conference controller supports encryption. When the control unit processes a message, it queries the network unit which, in turn, queries the encryption unit to determine if encryption is supported. The encryption section in the security window of the user interface is not built if encryption is not supported.

4.4 The Graphical User Interface

The graphical user interface (GUI) passes the input received from a local user to the control unit and displays the output passed to it from the control unit. Since minimizing screen real estate was important, *confcntlr* presents a small main window that displays the system status and controls for basic operations. Popup windows can be opened for specific categories of functions (e.g., local or remote settings, security features, general conference control). For user convenience, menus with predefined values are utilized along with entry fields to allow users to type their own values. The main window is shown below in Figure 11.



Figure 11: ConfentIr's main window

In the upper portion of the main window are the version number, buttons for displaying the tools running, and host addresses. The two columns of buttons labeled "Status" indicate which *vic*s and *vat*s are running locally and remotely (the left column in Figure 11 indicates that one *vic* and one *vat* are running on the local machine while the right column indicates that both *vic*s and one *vat* are running on the remote host). The Contact Host displays the address of the machine with which *confcntlr* is communicating and the Remote User displays the user who most recently performed remote control. In the lower portion of the main window are buttons to open the security, settings, and conference windows and to quit the program. The image in the lower left corner displays the remote control access level. On color monitors, the image displays red, yellow, and green, to correspond to the authorization levels "allow no one," "allow authorized users", and "allow anyone," respectively.

The conference window, opened when the "Conference" button is clicked, is shown in Figure 12. It displays the contact host, conference name, time-to-live (TTL), conference address and port for each video and audio tool, and buttons for starting and stopping local and remote tools or getting a remote host's settings. This window (and all subwindows) can be iconified with the "Dismiss" button. Values can be reverted to their defaults via the "Reset to Defaults" button.




Figure 12: The Conference Window

The local and remote menus are opened via the "Settings" button's pull-down menu, shown in Figure 13. They contain the parameters for the video and audio running on the local and remote hosts, respectively. The remote menu is shown in Figure 14 (the local menu is the same).




Figure 13: Main window with pulldown menus




Figure 14: Menu for setting remote vic and vat controls

Clicking on buttons labeled "Port..." or with an arrow open popup menus with predefined values. Figure 14 shows two of these menus. Figure 15 shows the "advanced audio window" that is opened by clicking on the "AdvAud" button.




Figure 15: Advanced Audio Window

The security window shown in Figure 16 displays the authorization levels, options for prompt and warning panels, an editable authorization list, and an editable encryption key. The prompt and warning panels may be used for setting permissions for remote control or notifying the user that an action has taken place. In Figure 16, options are chosen to "prompt to approve setting changes" and "turn on warnings." With the latter option, the local user is notified whenever a change is made by a remote user and she or he has not been prompted to manually approve the change. Examples of panels displayed for each of these options are shown in Figures 17 and 18. When a remote request is refused, a warning panel like those in Figures 19 and 20 may be displayed.




Figure 16: The Security Window




Figure 17: Prompt Panel to Approve a Remote Request for Setting Changes



Figure 18: Warning Panel for Notification of Changes Made by a Remote Host



Figure 19: Warning Panel to Display Denial of Setting Changes



Figure 20: Warning Panel to Display Denial of Action

Chapter 5

Algorithms

This chapter describes the primary data structures of the software components, explains the steps taken by *confcntlr* to carry out the actions invoked, and discusses how errors are handled.

5.1 Data Structures

The control unit's primary data structures are C character arrays to store requests and replies and Tcl arrays to store the parameter values. Each local and remote *vic* and *vat* is allocated its own array with its parameters as indices. These parameters include bandwidth, pid, format, etc. For convenience, the algorithms will refer to these arrays as "localtool" and "remotetool" to denote the tool being acted upon (e.g., localvic1 or remotevic2).

The setting and displaying of parameter values are achieved as follows. Controls in the graphical user interface are associated with Tcl variables. When a widget's value is changed, its associated variable is automatically updated and, if the variable is assigned a value anywhere in the program, the widget displays the new value. Thus, the GUI and the control unit share variables associated with widgets.

The network component utilizes application-specific data structures for storing messages. Since messages broadcast over the conference bus are exchanged between *confcntlr* and *vic* or *vat*, *confcntlr* defines the same fields for conference bus message structures as *vic* and *vat*, namely, a header and a character array for the data. The header includes integers to represent the message type, a "magic" constant, and the process identification (pid) of the sender. The character array will be referred to as the "text" field.

For messages transmitted over TCP connections, the network unit maintains a data structure with two fields: a "length" field and a character array to store the actual data. The character array will be referred to as the "text" field. The encryption unit maintains this same type of data structure.

5.2 Sequences of Operations

When the conference controller is launched, it initializes its components and enters the event loop. Upon termination, it checks for settings changes and performs cleanup before it exits. The pseudocode for initialization and termination are shown in Figures 21 and 22, respectively.

Init_App()
establish signal handler;
initialize Tcl/Tk;
implement Tcl/Tk and C interface;
set default values;
open TCP socket used for listening
for connection requests;
open multicast conference bus
sockets for sending/receiving
data;
create main window;
invoke Tcl/Tk event loop;

display "save panel";
write defaults file;
endif
close main TCP socket;
close conference bus sockets;
terminate each local vic/vat that
is running;
remove files created during
execution;
exit;

Terminate App()

if (setting changed)

Figure 21: Initialization

Figure 22: Termination

The following sections describe the sequences of operations for performing the actions invoked within the event loop. They will be presented in the following order: the algorithms used by the control unit for local operations, the algorithms used by the network unit for sending and receiving messages over the conference bus and TCP connections, the algorithms used by the control unit for initiating remote operations, and the algorithms used by the control unit for processing messages received from the network unit.

5.2.1 Local Operations

Launch of the videoconference tools on the local host can be initiated by the GUI or network unit. Upon receipt of a request to start all tools, each video and audio tool is executed in sequence. When *vic* or *vat* is started, *confcntlr* writes a Tcl script for that tool to set parameter values (which override *vic* or *vat* default values), define the types of conference bus messages *vic* or *vat* must recognize,

define procedures to invoke upon receipt of these messages, and define any other procedures to augment functionality. *Confcntlr* spawns *vic* and *vat* as child processes with command line arguments for options such as the conference address and name of the user-written Tcl script. Each unique process identifier (pid) is stored in the array corresponding to the tool started. The algorithm used by the control unit for starting one or more local tools (*vic* and *vat*) is given in Figure 23.

```
Start_Local_Tool(tools)
for each tool in tools do
write Tcl script for tool;
format command line arguments;
execute tool;
localtool(pid) := tool pid;
endfor
```

Figure 23: Starting vic and vat on Local Host

To stop one or more tools on the local host, the control unit retrieves the process identifier for each tool that is being terminated and terminates that process. If the tool has stopped at the request of a host other than the one that requested its execution, a notification is sent to the host that started the tool (referred to as the "launcher"). This algorithm is given in Figure 24.

```
Stop_Local_Tool(tools)
for each tool in tools do
kill localtool(pid);
localtool(pid) := -1;
if (launcher != local_host) then
send notification to launcher;
endif
endfor
```

Figure 24: Stopping vic and vat on Local Host

The algorithm for changing parameter values for *vic* or *vat* running locally can be invoked by the GUI or the network unit. When values are changed in the local menu and the tool is running, the control unit formats a message to *vic* or *vat* and invokes the network unit to broadcast the message. When the target process receives the message, it implements the change. The algorithm for dynamically changing local *vic* and *vat* settings is given in Figure 25.

```
Change_Local_Settings(parameters, tool)

if (localtool(pid) > 0) then

value := localtool(parameter);

format message;

CB_Send(message);

endif
```

Figure 25: Changing Local vic or vat Settings

5.2.2 Network Unit Algorithms

To send a message over the conference bus, the network unit calls CB_Send, which completes the fields of its message structure and broadcasts the message. When the network unit is called to receive a conference bus message, it calls CB_Receive. CB_Receive checks the process identifier (pid) in the header. If the pid does not match *confcntli*'s process identifier, the message may be from *vic* or *vat*; the data is forwarded to the control unit for further processing.

The algorithm used by the network component to send a TCP message assumes that its caller (the control unit) provides the socket descriptor, encryption

key, and message. Users can turn off encryption by entering an empty key. As discussed in Section 4.3, there is one version of the conference controller that can perform encryption and another version that cannot. Both versions have an encryption component which contains a function (referred to as "crypt_on") that returns a value to indicate whether encryption is supported. If encryption is supported, the network unit calls the encryption unit to perform the encryption and then writes the message to the TCP socket. The pseudocode for sending a TCP message is given in Figure 26.

```
TCP_Send(socket, data, key)
message.text := data;
message.length := length of data;
if (crypt_on() && key) then
encrypt(message.data, key);
message.length := message.length * -1;
endif
write message to TCP socket;
```

Figure 26: Sending a TCP Message

The algorithm for receiving a TCP message assumes that its caller (the control unit) provides the socket descriptor, the encryption key, and buffers for returning the message along with values indicating whether encryption is supported and whether the message was encrypted. The network unit reads the length and then the message. If the length is a negative integer, the encryption unit is called to decrypt the message. The network unit returns the plaintext message and values that indicate whether encryption is supported and whether the message was encrypted. If a conference controller that supports encryption

receives an unencrypted message, it returns an error code. The pseudocode for receiving a TCP message is given in Figure 27.

```
TCP_Receive(socket, key, data, crypt_support, encrypted)
   read message.length from socket;
   if (message.length < 0) then
        message.length := message.length *-1;
       encrypted := true;
   else
       encrypted := false;
   endif
   crypt_support := crypt_on();
   if (!crypt_support &&encrypted) then
           data := "was encrypted";
           return;
   endif
   read from socket message.length bytes into message.text;
   if (crypt support && encrypted) then
          decrypt(message.text, key);
   endif
   data := message.text;
   return number of bytes read;
```

Figure 27: Receiving a TCP Message

5.2.3 Initiating Remote Operations

Remote operations include starting and stopping *vic* and *vat* on a remote machine, changing parameter values of a tool running on a remote machine, and obtaining another host's settings. The network unit waits for a reply only if the request is to get another host's settings.

When users request a remote operation, the control unit formats a request message and calls the network unit to open a TCP connection with the contact host and send the message.

The message types are:

- "start_tool" to start vic or vat (e.g., start_vic1)
- "start all" to start both vics and vat
- "stop_tool" to stop vic or vat (e.g., stop_vic1)
- "stop_all" to stop all tools running
- "cb_tool" to change the settings on a tool that is running (e.g., cb_vic1)
- "get_params" to obtain a host's settings.

The format of each message is: "message_type user@host arguments," where the arguments vary with respect to the message type. For example, the arguments for a "start_tool" message list the parameter values of vic or vat. The arguments for "stop_tool" and "stop_all" requests are the pids of the tools being stopped. The arguments for a "cb_tool" request are a list of the parameters to change and a list of their new values. There are no arguments for "get_params" requests. (A "get_params" request is automatically sent to the specified contact host when confcntlr is started and when the user changes the contact host.) The algorithm for requesting a remote operation is given in Figure 28.

Figure 28: Requesting a Remote Operation

5.2.4 Responding to Messages Received from the Network Component

To read messages, the control unit invokes the network unit from either a file handler or from a routine that is performing sequential I/O. Each message is processed by a routine that is defined for its message type. In describing how the conference controller handles the messages it receives, we will assume that, if the message arrived on the conference bus, CB_Receive has been called.

A conference bus notification is in the format: "action pid arguments." For example, the message "changeParam 1234 transmit 0" means that process number 1234 turned off transmission and the message "adios 1234" means that process number 1234 was terminated. The control unit identifies the action and, if it is recognized, it searches the arrays for local tools until it finds a matching pid and makes the necessary updates.

To respond to a TCP request message, the control unit identifies the sending host, checks whether the message is encrypted, and determines if encryption is supported. If encryption is supported and the message is encrypted, additional security checks are performed; otherwise, an error message is sent. If remote control access is being granted, the next step is to parse the action and the arguments from the request and call a subroutine to carry out the requested action. When the subroutine returns, a reply is sent and the TCP connection is closed.

This algorithm, Process_TCP_Request, is shown in Figure 29, .

```
Process_TCP_Request(message, crypt_support, encrypted)
   if (message == "was encrypted" && !crypt_support) then
        TCP_Send("encryption not supported");
        close TCP connection;
        return;
   endif
   check authorization;
   if (requestor is not authorized || remote control is disabled) then
        TCP Send("operation not allowed");
        close TCP connection;
        return;
   endif
   identify the action;
   if (crypt_support && !encrypted) then
        TCP_Send("not authorized");
        close TCP connection;
        return;
   endif
   if ((action == "start_tool") || (action == "start_all")) then
        identify the tool and requested values;
        reply := Do_Start(tool, requested_values);
   else if (action == "stop_tool") then
        identify the tool;
        reply := Do_Stop(tool);
   else if (action == "cb_tool") then
        identify the tool, parameters, and values;
        reply := To_Cb(tool, parameters, values);
   else if (action == "params") then
        reply := Send_Settings();
   else
        /* invalid request */
        reply := error message;
   TCP_Send(reply);
   close TCP connection;
```

Figure 29: Processing a TCP Request

The subroutines called are: Do_Start for "start_tool" or "start_all" requests, Do_Stop for "stop_tool" requests, To_Cb for "cb_tool" requests, and Send_Settings for "params" requests. Do_Start and To_Cb use the same algorithm to change settings, Do_Changes, given in Figure 30.

```
Do_Changes(tool, parameters, new_values)
    foreach parameter in parameters do
        if (parameter is supported && new value of parameter != localtool(parameter)) then
            add parameter and new_value to a list of changes;
            if (prompt option == "on" for this type of parameter) then
               add parameter and its new_value to lists for prompt panel;
            endif
        endif
     endfor
     if (there are items for a prompt panel) then
         display prompt panel;
     endif
     foreach parameter in list of changes do
         if (permit(parameter) == "allow") then
            if (parameter is not on prompt panel list) then
                 add parameter and its current value of parameter to lists for warning panel;
            localtool(parameter) := new_value of parameter;
            add parameter to "rejects" list;
         endif
      endfor
      return "rejects" list and warning panel list;
```

Figure 30: Changing Parameter Values

The arguments to Do_Changes() are the tool, a list of parameters to change, and a list of requested values. The first step is to check the given lists to make sure that the parameters are supported and that the requested values are different from the current values. Next, default permissions are assigned to each parameter to be changed. If a prompt option is set for a given type of parameter, the GUI is invoked to display a dialog box so that the user can override the default permission. Changes are made if the permission is "allow". Do_Changes returns a list of parameters not changed and a list of parameters that were changed according to their default permissions along with their original values. The

"rejected" parameters are sent in the reply and the lists of changes made are used for warning panels.

The Do_Start subroutine, shown in Figure 31, obtains the permission value for a "start" action and returns a "permission denied" message if the action is not allowed. Otherwise, it continues by calling Do_Changes to set parameters to their requested values and Start_Local_Tool to execute *vic* and/or *vat*. The routine invokes the GUI to display necessary panels and updated values.

```
Do_Start(tool, new_values)
  if (("prompt to approve all actions"==true) && ("prompt to approve start/stop"==true)) then
     display prompt panel;
     permit(start) := default permission value;
  endif
  if (permit(start) == "not allow") then
      return "permission denied";
  general_parameters := "version conference_name ttl";
  Do_Changes(general_parameters, values for general_parameters);
  foreach tool do
      parameters := parameters applicable to tool;
      Do Changes(parameters, new values for parameters):
      concatenate prompt panel lists returned by Do_Changes;
      concatenate warning panel lists returned by Do_Changes;
  endfor
  Start_Local_Tool(tool);
  if ((list for warning panel != null) && ("turn on warnings"==true)) then
      display warning panel;
  endif
  reply := pid(s) of tool(s) started;
  concatenate "rejects" list(s) and append to reply;
  update display; /* configure labels on local 'start' buttons */;
  return reply;
```

Figure 31: Starting vic or vat in Reponse to Remote Request

To change the settings on *vic* or *vat*, Do_Changes is called with a parameter list and requested values. If the change is made, the control unit formats a conference bus message and invokes the network unit to send it. The GUI displays a warning panel if the change was made without a prompt panel. The pseudcode is given in Figure 32, To_Cb.

```
To_Cb(tool, parameters, values)
    reply := Do_Changes(parameters, values);

/* if Do_Changes returns a null "rejects" list, the requested changes were approved*/
    if ("rejects" == null) then
        if (("changed_parameters" list is not empty) && ("turn on warnings"==true) then
            display warning panel;
        endif
        Change_Local_Settings(parameters, tool);
    endif
    update display;
    return reply;
```

Figure 32: Changing Vic or Vat Settings in Response to Remote Request

To stop *vic* or *vat*, the Do_Stop subroutine calls Stop_Local_Tool, if the action is permitted. It invokes the GUI when necessary to display a prompt panel and update the status, and it returns a reply to Process_TCP_Request.

The Send_Settings subroutine lists the values of all the parameters on the responding host as well as what tools are running and what video and audio devices it has. It returns a concatenated list. Figure 33 shows the pseudocode.

```
Send_Settings()
list general parameter values; /* version number, conference name, ttl */
foreach tool do
list parameter values;
endfor
list tools running on local host;
list video and audio devices on local host;
return concatenated list;
```

Figure 33: Sending Local Settings

Since a reply to a request may not be received immediately after the request was sent, the replies include the name of the sending host and the action that was requested. The format of the reply depends upon its type. For example, replies to "start" or "stop" requests include the pid(s) of the tools(s) being started or stopped as well as a list of the tools running. The replies to "start" and "cb_tool" requests list any parameters whose changes were rejected. The replies to "get_params" requests include the values of all parameters, a list of tools running, and lists of the video and audio devices on the sending host. If an action failed, the reply contains an error code.

When the control unit receives a reply, it identifies the sender and action, and then parses the remaining fields of the message. If the requested action was not carried out (e.g., permission was denied or there was an error), the GUI displays a warning panel. If the contact host is the same as the sender, the control unit updates the parameters of the remote tool with the values specified in the reply and the GUI updates the display. If the contact host is not the same as the

sender, *confcntlr* does not overwrite any values (the current status applies to the current contact host). When a reply to "get_params" is received, the controls for the video and audio devices and audio thresholds are configured to reflect what is supported on the remote host.

5.3 Error Handling

ConfentIr checks for system call and encryption failures and errors in user input. Fatal errors include failures in creating the socket on which to listen for TCP connection requests and failures to create the conference bus sockets. If these occur, a message is written to standard error and the program exits. Nonfatal errors include errors in creating sockets for sending requests, reading or writing sockets, and encrypting or decrypting messages. If a nonfatal error occurs, confentIr writes a message to standard error, sends an error code in its reply, or displays a notification panel, depending on the type of error. For example, TCP socket read errors include reading less than "length" number of bytes or reading a request is that is unrecognized. If the socket is open, its file handler is deleted and the socket is closed. If the network unit cannot receive a conference bus message, it writes a message to standard error. Processing is resumed with the next event on the event queue.

When the network unit receives a TCP message, it sets a timeout value in its TCP_Receive routine. The read blocks until either data is read or it reaches

the timeout value. When called from a file handler, TCP_Receive will not time out since the routine is only called when there is data to be read. However, when TCP_Receive is called from a routine that calls a read immediately following a write (such as in getting another host's settings), the read may time out. To reduce this possibility, prompt panels will time out if the user does not respond within a fixed amount of time.

To reduce or avoid socket errors, the conference controller verifies the name of the contact host input by the user. Whenever the control unit requests a TCP connection, the network unit checks that the address of the remote host is specified and that it is a valid unicast address. If the address is empty, unidentified, or multicast, a warning panel is displayed so that the user can edit the name of the contact host and no socket calls are made.

If there is an encryption incompatibility (e.g., a conference controller that does not support encryption receives an encrypted message or a conference controller that supports encryption receives an unencrypted message), the receiver writes a message to standard error and writes an unencrypted error code as a reply. If the sending and receiving hosts support encryption but their keys do not match, decryption fails and returns an error code to the network unit. The network unit writes an error message to standard error and writes an encrypted error message to the remote host (to force its decryption to fail).

Chapter 6

Summary and Future Work

The capability of multicast has inspired research into building virtual laboratories and developing multimedia conference tools. Current efforts have focused on video, audio, and shared workspace applications and their infrastructures. Conference management has included conference announcement, creation, and invitation, and resource management. The first two chapters presented an overview of this research. However, most of the current management tools launch and forget media, and do not support remote setting changes for media that are executing.

This thesis described the design, development, and implementation of *confentlr*, a conference controller that enhances the management of the *vic* and *vat* videoconference tools. It discussed the requirements and architecture, described the design and implementation of the functional components, and presented the algorithms used.

By allowing remote control of video and audio, *confcntlr* has changed the way the videoconferencing tools are used. Users no longer need to be present at all sites. Instead, the person who is watching the transmission and cares most about how it is coming in can control the transmission. Also, by presenting a uni-

fied interface, *confcntlr* has made it easier to manage the separate media tools that are running concurrently.

Confcntlr is now used as the primary interface to the videoconferencing tools in the Spectro-Microscopy Collaboratory. It has greatly enhanced the usability of the videoconference tools in the collaboratory. The researchers at the transmitting site can spend more time on scientific experimentation since they no longer have to manage the conference. The confcntlr source code and binaries for selected architectures can be obtained from the pointers listed in Appendix A.

However, further enhancements to the conference controller's usability can be made. Since many conference participants may be PC users, *confcntlr* should be ported to the Windows95 environment. Future work might include changing the static support of two *vic*s and one *vat* to a more dynamic design. For example, a "create" feature can be used to allow users to specify the tools they want to manage and the windows and variables could be configured accordingly.

Future work might also include incorporating the following features. It may be helpful to add an email or "call up" facility by which users can hold private conversations. While *confcntlr* can be used for public sessions (since it can be launched by *sdr*), conference participants may not know who else is running *confcntlr*. Currently, participants can use the members' lists in the *vic* and *vat* win-

dows to attempt to contact other hosts. Consideration should be given to integrating the participants' lists within the *confcntlr*'s graphical user interface and/ or having *confcntlr* announce itself on the MBone when it is started. Furthermore, while notifications are queued for warning panels, it may be worthwhile to provide an option to write notifications to a log file. Also, if a request is received while a modal panel is displayed, the requesting host is sent a "busy signal." If this occurs too frequently, requests might be queued or a multithreaded approach might be taken.

References

- 1. Agarwal, D., Johnston, W., Loken, S., and Tierney, B., "Tools for Building Virtual Laboratories." *Proceedings of Computing in High Energy Physics, Rio de Janeiro, Brazil* (September 1995): 3-11.
- 2 Agarwal, D., Sachs, S., and Johnston, W., "The Reality of Collaboratories." *Proceedings of Computing in High Energy Physics, Berlin, Germany* (April 1997): Paper Number 329.
- 3 Anderson, B., "Providing Explicit Support for Social Constraints: In Search of the Social Computer." *ACM CHI96 Online Proceedings: Doctoral Consortium, Vancouver, British Columbia, Canada* (April 1996); available from http://www.acm.org/sigchi/chi96/Doctor-Consort; Internet; accessed 21 September 1997.
- 4 Cerf, V., Cameron, A., Lederberg, J., Russell, C., Schatz, B., Shames, P., Sproull, L., Weller, R., and Wulf, W., *National Collaboratories: Applying Information Technologies for Scientific Research*, Washington, D. C.: National Academy Press, 1993.
- 5 Clark, L., and Sasse, A., "Conceptual Design Reconsidered: The Case of the Internet Session Directory Tool." *UCL Computer Science Research Note*; available from http://www-mice.cs.ucl.ac.uk/merci/publications.html; Internet; accessed 23 September 1997.
- 6 Comer, D., *Internetworking with TCP/IP: Principles, Protocols, and Architecture*, 2d ed., Volume I, New Jersey: Prentice-Hall, 1991.
- 7 Eriksson, H., "MBONE: The Multicast Backbone." *Communications of the ACM* (August 1994): 54-60.
- 8 Garfinkel, S., and Spafford, G., *Practical UNIX and Internet Security*, 2d ed., California: O'Reilly and Associates, 1996.
- 9 Handley, M., Kirstein, P., and Sasse, A., "Multimedia integrated conferencing for European researchers (MICE): piloting activities and the conference management and multiplexing centre." *Computer Networks and ISDN Systems*, Volume 26 (November 1993): 275-290.
- 10 Handley, M., and Wakeman, I., "CCCP: Conference Control Channel Protocol: A scalable base for building conference control applications." *Proceedings of the ACM Conference SIGCOMM*, NewYork: ACM Press, 1995.

- 11 Jacobson, V., and McCanne, S., *VIdeoConference* [version 2.8], Lawrence Berkeley National Laboratory, Berkeley, California; available from http://www-nrg.ee.lbl.gov/vic; Internet; accessed 6 June 1997.
- 12 Jacobson, V., and McCanne, S., *Visual Audio Tool* [version 4.0b2], Lawrence Berkeley National Laboratory, Berkeley, California; available from http://www-nrg.ee.lbl.gov/vat; Internet; accessed 6 June 1997.
- 13 Kirstein, P, Handley, M., Sasse, A., and Clayman, S., "Recent Activities in the MICE Conferencing Project." *Proceedings of INET95, Internet Society, Honolulu, Hawaii* (June 27-30).
- 14 Kouzes, R., Myers, J., and Wulf, W., "Collaboratories: Doing Science on the Internet." *Computer* (August 1996): 40-46.
- 15 Lyonnet, F., "Rendez-Vous", the next generation videoconferencing tool, INRIA, France; available from http://www.inria.fr/rodeo/rv; Internet; accessed 23 September 1997.
- 16 Macedonia, M., and Brutzman, D., "MBone Provides Autio and Video Across the Internet." *IEEE Computer Magazine* (April 1994): 30-36.
- 17 McCanne, S., and Jacobson, V., "vic: A Flexible Framework for Packet Video." *ACM Multimedia* (November 1995): 1-19.
- 18 Ousterhout, J., *Tcl and the Tk Toolkit*, California: Addison-Wesley Publishing Company, 1994.
- 19 Sasse, A., Bilting, U., Schulz, C., and Turletti, T., "Remote Seminars through Multimedia Conferencing: Experiences from the MICE project." *Proceedings of INET94, Internet Society* (June 1994): 251/1 251/8.
- 20 Schooler, E., "Conferencing and collaborative computing." *ACM Multimedia Systems Journal*, Volume 4, Number 5 (October 1996): 210-225.
- 21 Schooler, E., "Cast Study: Mulimedia Conference Control in a Packet-switched Teleconferencing System." *Journal of Internetworking: Research and Experience*, Volume 4, Number 2 (June 1993): 99-120.
- 22 Schulzrinne, H., "Dynamic Configuration of Conferencing Applications using Pattern-Matching Multicast." 5th International Workshop on Network and Operating System Support for Digital Audio and Video(April 1995): 231-242.

- 23 Stevens, W. R., *UNIX Network Programming*, New Jersey: Prentice-Hall PTR, 1990.
- 24 Turletti, T., "The INRIA Videoconferencing System (IVS)." *ConneXions--The Interoperability Report*, Volume 8, Number 10 (October 1994): 20-24.
- 25 Turletti, T., and Huitema, C., "Videoconferencing on the Internet." *IEEE/ACM Transactions on Networking*, Volume 4, Number 3 (June 1996): 340-351.
- 26 Welch, B., *Practical Programming in Tcl and Tk*, New Jersey: Prentice-Hall PTR, 1995.

Appendix A

Further Information

The source code and binaries for *confcntlr* can be obtained at: ftp://george.lbl.gov/pub/mbone/confcntlr

Information on how to use and obtain MBone tools is available at: http://www-itg.lbl.gov/mbone

Information about the Spectro-Microscopy Collaboratory is available at: http://www-itg.lbl.gov/BL7Collab

Explanations of how to interface with *vic* and *vat* via the conference bus and how to build a Tcl/Tk program as a standalone C program are available at:

http://www-itg.lbl.gov/mbone/confcntlr

Appendix B

Confentir: User Manual

DESCRIPTION

Confcntlr is a conference controller which is intended to allow easier access to, control of, and coordination of a videoconference between remote sites. It should be run on all the machines participating in a videoconference session and used to control vic and vat. Confcntlr is a graphical user interface and communication tool. Through the graphical user interface, you can initiate actions and set the local and remote video and audio parameters. After confcntlr is started, confcntlrs running on remote hosts can communicate with it to start or stop the media tools or to change settings for tools that are already running. Requests and replies between confcntlrs are exchanged over the Internet. Messages between vic or vat and confcntlr on the same host are sent via the local multicast "Conference Bus."

Confcntlr is meant to control only one videoconference. However, multiple confcntlrs can be executed on one host. Each confcntlr running on the local host must have a unique port on which it listens for connection requests from remote confcntlrs. Confcntlrs running on different hosts and controlling the same conference must have the same port number. The conference controller must be started before vic and vat and each confcntlr can launch two vics and one vat, either locally or remotely. Security features provide access control and two versions of confcntlr are available: confcntlr-crypt (which supports encryption of messages sent over the network) confcntlr (which does not perform encryption).

PLATFORM AND SYSTEM REQUIREMENTS

Confcntlr was developed on a SUN workstation and ported to SGI. The latest version (beta V0.4) has been tested on Solaris 2.5.1 and Irix 6.2. The same hardware and networking capabilities required for *vic* and *vat* are required for *confcntlr*. (See http://www-itg.lbl.gov/mbone.)

COMPILATION

If you have the source code and Makefile for *confcntlr* (or *confcntlr-crypt*), make sure that Tcl/Tk (v7.5/4.1) is installed on your system. Make sure that *vic* and *vat* are also installed on your system. Then follow the steps below to compile the conference controller.

To build *confcntlr* (nonencrypted version):

Edit the following lines in the Makefile so that you have the correct include and library paths for Tcl/Tk:

```
INCLUDE_TK =
INCLUDE_TCL =
INCLUDE_X11 =
LIB_TCLTK =
```

Run "make confcntlr".

To build *confcntlr-crypt* (encrypted version):

Make sure that the ssleay library (SSLeay-0.6.4) is also properly installed. Edit the following lines in the Makefile so that the include and library paths are correct for the Tcl/Tk and encryption (ssleay) libraries

```
INCLUDE_TK =
INCLUDE_TCL =
INCLUDE _X11 =
INCLUDE_CRYPT =
LIB_TCLTK =
LIB_CRYPTO =
```

Run "make confcntlr-crypt". You might want to rename the binary to "confcntlr".

The binary will be created in the current working directory.

INSTALLATION

Install the binary in the desired directory (e.g., /usr/local/bin). Install the dot files (.confcntlrrc and .ccauth) in your home directory. Install the sdr plugin (sdr2.plugin.S50.control.tcp.*.confcntlr) in \$HOME/.sdr/plugins. The plugin is necessary if

you want to create a conference session with *sdr* and have *sdr* launch *confcntlr*. .confcntlrrc is the defaults file. It contains entries of parameters and values used to override system defaults. .ccauth is an authorization list; its entries are users who will be allowed remote access to the conference controller. Both files should be edited so that their values are meaningful to your environment. The format of entries for each file must be strictly adhered to.

In .confcntlrrc, you probably want to make the following changes:

Change the default contact host to a meaningful value in the line:

"hostaddr# warner.bros.edu"

Change the list of contact hosts in the line:

"hostlist# warner.bros.edu remote.machine.com"

Change the video devices to those that are available on your machine in the line:

"deviceList# sunvideo sunvideo-1"

Change the video input jacks to those that are available on your machine in the line:

"devportList# Composite-1 S-Video"

Change the list of audio input and output devices to those that are available on your machine in the lines:

"audioInputDevices: mike linein"

"audioOutputDevices: speaker headphone linout"

Change the list of ports in the line:

"portlist# 12345 12347 12349"

Change the list of conference addresses in the line:

"addrlist# unicast 224.35.36.37"

Change the default value for conference addresses in the lines:

"localvic1.confaddr# unicast"

"localvic2.confaddr# unicast"

"localvat.confaddr# unicast"

Change the default conference name in the line:

"confname# CONFERENCE"

Change the default port numbers in the lines:

"localvic1.port# 12345" "localvic2.port: 12347" "localvat.port: 12349"

In .ccauth:

Change the list of users and hosts to those users and remote hosts that have access control to your program. An asterisk can be used to mean "all". The line "*@remote.machine.com" means "any host" at remote.machine.com.

EXECUTION

SYNOPSIS

```
confcntlr [ -f filename ] [ -p port ]
confcntlr-crypt [ -f filename ] [ -k key ] [ -p port ]
```

OPTIONS

- -f Use *filename* as defaults file. If *filename* is not found in the home directory, system defaults are used and the current settings are saved to this file upon termination. If not specified, the home directory is searched for .confcntlrrc.
- -k Use *key* as the encryption key for the encryption version of *confcntlr*.
- -p Set the port on which *confcntlr* listens for connection requests from remote *confcntlr*s. Specify *port* as an integer greater than 6000. If not specified, the default 62525 is used.

OPERATION

Starting/stopping tools, changing settings, and communicating with remote hosts are controlled via the windows. The main window shows the conference status and has buttons for general control (e.g., quitting the program and bringing up the windows for setting options, changing settings, and starting tools).

MAIN WINDOW

Remote Host Names

The entry field labeled "Contact Host" shows the name of the machine to connect to. Use this field to type or edit the name of the remote site you want to communicate with. Do not use the same name as the local host and do not use a multicast address. To bring up a menu with predefined addresses, click on the button with the arrow. If you press the return key in the entry field or click on a button and *confcntlr* is running on that host, you will get that host's session status, settings, and video/audio devices. You can change the list of host addresses or add new addresses by editing the following line in the defaults file (e.g., \$HOME/.confcntl-rrc):

hostlist# <address1> <address2> ... <addressN>.

The field labeled "Remote User" indicates the most recent user who started/ stopped a tool or changed the settings from a remote host. The format is: user@hostname.

Status

The main window shows the authorization level and which tools are running. The left column of buttons labeled "Status" indicates the tools running on the local host and the right column indicates tools running remotely, in order of video 1, video 2, and audio. A red button indicates that a tool is running. The stop sign image indicates the authorization level. If it is green, control access to *confcntlr* is granted to anyone. If it is yellow, control is allowed by hosts on the authorization list in the home directory. If it is red, no one is allowed control access.

Subwindows

Click on the buttons labeled "Settings," "Conference," and "Security" to bring up the windows described below. At startup, if you specify a Contact Host and *confentlr* is running on that host, you will automatically get its settings.

Quitting Confentlr

To quit the program, click on the button labeled "Quit". If changes were made, you will be prompted about saving the changes.

LOCAL WINDOW

This window allows you to change the settings for video and audio tools running on the local host. There is a section for each tool with the titles "vic 1", "vic 2", and "vat" for video 1, video 2, and audio, respectively.

For video, a dialog box will appear if the bandwidth or frame rate is set to a value that exceeds the recommended limit. If you still want to use this value, click on the button labeled "USE ANYWAY." If you want to edit the value, type in the entry field and then click "SET." If you want to go back to the default value, click on "SET TO DEFAULT." If you want to use the previous value, click on "UNDO CHANGE."

Conference Name Extension

The entry field labeled "ConfName Ext" is for specifying an optional extension to the conference name for the video or audio. The characters "/", "#", and "@" are not allowed since they are used by the program.

Video Transmission

To start or stop video transmission, click on the button labeled "Transmit Video". A red checkbox indicates transmission is "on".

Video Settings

The bandwidth, frame rate, quality, and device may be changed via their pulldown menus or typing in their entry fields and ending with the return key. The format and input (Port...) can be changed only via their pulldown menus.

If you want the value you typed for quality to be kept as the quality associated with the current format, press the return key after typing the entry.

Since different video formats support different quality ranges, changing the video format will automatically change the range of values for the video quality. Cellb does not support quality, so if cellb is the selected format, the quality menubutton and entry field are disabled.

Audio Settings

The audio format can be changed by either typing in its entry field or clicking on the button labeled with an arrow. Lecture mode, recv-only, and "keep audio" can be turned on and off by clicking in their checkboxes. A red checkbox means "on." Clicking on the "listen" and "talk" checkboxes mutes or unmute the output and input devices; red means "unmuted". To change a device, click on the button labeled with an arrow below the "talk" or "listen" checkbox. Then click on your selection. The image to the left of the button displays the current device. You may change the devices available by editing the list of values for "audioOutputDevices" and "audioInputDevices" in the defaults file.

The sliders below the devices are for changing the gain levels. The selected output mode applies to the current output device. External echo cancellation ("ExtEchoCancel") is available only if the "localvat.echoCancel" value is "true" in the defaults file.

The bitmaps that indicate the current input/output devices were taken from the *vat* source code.

Advanced Audio Settings

Clicking on the button labeled "AdvAud" will bring up a window with controls for local audio tests. If your \$HOME/.vat.tcl file contains a procedure for talk thresh-

old, echo threshold, and echo suppression time, sliders for setting these values will also be displayed. (See SETTING DEFAULTS below and/or the mbone web page at http://www-itg.lbl.gov/mbone for more information.)

Dynamic Changes

You do not need to stop and restart the video to change the following: transmission, bandwidth, frame rate, format, quality, device, and input jack. If you type in an entry field, end with the return key.

You do not need to stop and restart the audio to change the following: output/input device, output mode, output/input gain, or threshold levels. Lecture mode, recv-only, "keepaudio," and muting/unmuting devices can be turned on and off without stopping and restarting *vat*.

If you click the "quit" button in the *vic* or *vat* main window, or if you click *vic*'s transmit button, *confcntlr* will be sent a message and it will update its controls.

Reverting to Defaults

To go back to default values, click the button labeled "Reset to Defaults." To hide the window, click on the "Dismiss" button.

REMOTE WINDOW

This window is used to change the settings for video and audio tools on a remote host. It works in the same way as the "local window."

When a remote host sends its settings (as in response to clicking on "Get Remote Settings" or a change in Contact Host), the remote and conference windows display the values.

For *vat*, the external echo cancellation and threshold sliders are disabled and grayed out if *confcntlr* hasn't obtained the contact host's settings or if the contact host doesn't support these features.

CONFERENCE WINDOW

To specify a name for the conference, type in the entry field labeled "Conference Name." The conference name is optional and can be the same or different for each session. The characters "/", "#" and "@" may not be used since they have special meaning to the program.

Conference Address, Port, and Time-to-Live

A conference address, port, and time-to-live value must be specified. Each tool has its own conference address and port. The value specified for the video or audio applies to both the local and remote tool. The conference address may be the same or different for each tool, but the ports must be different. (You can run *sdr* to get the conference address and port if they are unknown.)

To change the values, click on the button labeled with an arrow and then click on a selection in the pulldown menu, or type in the entry field and end with the return key.

The conference address is the address to which the video and audio tools transmit. If "unicast" is specified and there is no "Contact Host", the local *vic/vat* will transmit its video/audio to the local host. If there is a "Contact Host" and both local and remote programs are started, they will transmit to each other. Otherwise, transmission will be to the address specified.

Starting/Stopping Tools

To start/stop tools on the local host, click on the selected button in the column on left side of the lower portion of this window. To start/stop tools on a remote host, click on the selected button in the column on the right side of the lower portion of this window.

When a local tool is started, the square turns red and the label changes to "stop" to indicate that next action available is to stop the tool. When you start a remote tool, a message is sent to the contact host and a reply is expected. The start button turns pink until the reply is received. This could be delayed if the network is slow or if the remote user is manually setting control permissions (see SECURITY WINDOW).

Clicking on a "Start All" button will start all three tools. The "Stop All" button will stop all tools that are running.

Getting Remote Settings

To get a remote site's settings, type the contact host name and press the return key, select a host from the menu, or click on the button labeled "Get Remote Settings." The values in the remote window and the status buttons will be updated. The video devices, video input ports (jacks), and the audio threshold and external echo cancellation features will be enabled or disabled, depending on what is supported by the contact host.

SECURITY WINDOW

This window contains controls for setting the authorization level, viewing/editing the authorization list, selecting the prompts and warnings, and editing the encryption key if you are running the version that supports encryption.

Access Control

There are three authorization levels: allow any remote host to make a request, allow only users on the authorization list to make requests, or do not allow anyone to make a request. To change the authorization level, click on the desired radiobutton. The stop sign image in the main window will change color accordingly. The authorization list can be viewed or edited via the scrollbar text field. When you quit *confcntlr*, if this list has been changed, a panel will appear to ask if the changes should be saved to the \$HOME/.ccauth file.

Setting Permissions for Actions

If you want to manually approve start/stop". If you want to approve changes in conference address, port, time-to-live, or conference name, click "on" the button labeled "Prompt to approve address/ttl/name changes." If you want to approve other changes, click "on" the button labeled "Prompt to approve setting changes." If you want to manually approve every request, click "on" the button labeled "Prompt to approve all actions". If an action is denied, the requesting host will be notified.

When you are not prompted to set the permission for a request, a warning panel will appear to notify you that the change has been made. If you do not want to receive these warnings, click "on" the button labeled "Turn off warnings."

Encryption

If you are using encryption, all hosts participating in the conference must use the same key. To turn off encryption, erase the key or use a blank space or tab as the first character. You may change this key, but only after all participants have agreed on the new key. The distribution of *confcntlr* from LBNL via the World Wide Web does not support encryption due to U.S. export controls. In this case, this section is missing in the security window.

SETTING DEFAULTS

When *confcntlr* starts, settings are read from the \$HOME/.confcntlrrc file, or from the defaults file in the home directory that is specified with the -f option. If there is no defaults file, the program supplies the values and displays a notification panel. When you quit the program, if values are different from those at startup, a panel will appear to ask whether you want to save the changes. Click on the button labeled "Save Settings" to update the defaults file if it exists or create one if it does not exist.

In order to associate a quality value with a specific format for the video, the numeric value can be edited in the \$HOME/.confcntlrrc file in the following lines:

```
*vic.jpeg# xxx
*vic.h261# xxx
*vic.nv*# xxx
```

WARNING: If the format of the defaults file is not held to strictly, the entry will not be read! The list of users with access control is kept in the \$HOME/.ccauth file. If you change this list in the security window, when you quit the program, you will be asked if you want to save the changes to this file. If the file does not exist, it will be created.

As described in the *vic* and *vat* documentation, both of these tools allow user customization by specifying tcl commands in a \$HOME/.vic.tcl (or \$HOME/.vat.tcl) file and in a script that can be specified with the "-u" command line option. Although it is not required, a "user_hook" procedure can be included in these files. When *confcntlr* starts a session, it writes a script with a user_hook procedure and starts the video and audio with the "-u" option. Since this script is executed AFTER the \$HOME/.vic.tcl (or \$HOME/.vat.tcl) scripts, the user_hook procedures in the \$HOME/.vic.tcl and \$HOME/.vat.tcl files will be overridden. To have them execute, rename "proc user_hook" to "proc confcntlr_hook" in the \$HOME/.vic.tcl and \$HOME/.vat.tcl files.

If there is a user_hook procedure but no confcntlr_hook procedure in a \$HOME/.vic.tcl or \$HOME/.vat.tcl file, you will get a warning panel one time only, the first time a session is started.

SESSION DIRECTORY SERVICES

sdr will launch *confcntlr* if you have the appropriate plugin (available from http://www-itg.lbl.gov/mbone/confcntlr).